

---

Subject: Brenbot Problem

Posted by [mark72091](#) on Tue, 01 Jun 2004 16:31:12 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Sorry if this was posted somewhere else but I looked through the first 4 pages on the forums and found nothing also did a search which came up with nothing here is my problem I installed LFDS for RedHat 8.0 and LFDS Wrapper for 8.0 Im running on RedHat 8.0 so it works fine but when i try to run brenbot i get Can't connect to LFDS Wrapper! and it keeps saying that until i shut it down can you tell me what im doing wrong?

Starting up renrem thread...

BRenBot 1.35 linux.

brenbot is Copyright 2003-2004 by Blackhand Studios. All Rights reserved.

Connecting to RenGuard...

Could not load ssc\_ignore.txt - No users are being ignored by RenGuard!

Got serverlist..

Sending to ... 66.79.176.170:100

Opening server port ...

IRC Initialization...joining 68.158.244.9:6667

my nick is IAserv04

Setting up protected nickname thread...

Setting irc refresh thread...

Can't connect to LFDS Wrapper!

Connected to RenGuard.

Connecting to IRC... waiting for welcome message

Got Server Welcome Message...

Identifying with NickServ...

Joining IRC Channel...

Connection to renrem not possible. Can't send msg BlazeRegulator/BlazeRenBot 1.35 linux starting up...

Connection to renrem not possible. Can't send game\_info

Connection to renrem not possible. Can't send player\_info

IRC: IAserv04 :+wx

---

---

Subject: Brenbot Problem

Posted by [\[HLOW\]Tomten](#) on Tue, 01 Jun 2004 20:45:16 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

You need to add ssc\_ignore.txt yourself, pico ssc\_ignore.txt (add playername)

When you start ./renegade\_server it will give you a port number, listen os port nr blabla or something.

Add that port number in your setup.ini file

RemoteAdminPort = 4853 for exampel

RemoteAdminIP = 10.3.31.18 (Whatever)

Then goto the brenbot.cfg file:

BotMode = LFDS

#--Remote Admin Settings-----

# The next 3 lines should be the same info that is in your server.ini

# Note: Although it says "Linux" its the same for Win32

RenRemLinuxHost = 127.0.0.1 (as before, whatever)

RenRemLinuxPort = 4853 (exampel)

RenRemLinuxPassword = XXXXXXXX

This should solve your problem.

---

---

Subject: Brenbot Problem

Posted by [mark72091](#) on Tue, 01 Jun 2004 21:17:28 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

ok That worked thanks alot

---

---

Subject: Brenbot Problem

Posted by [\[HLOW\]Tomten](#) on Wed, 02 Jun 2004 05:50:29 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

no problem

---