## Subject: 4.0 Server Damage

Posted by cAmpa on Mon, 07 May 2012 13:46:21 GMT

View Forum Message <> Reply to Message

I got a few question's about these changes.

- 1. What is the different between "StockDamageHook" and "TtDamageHook", how do they work? When do they get triggered and when not?
- 2. On 3.4 scripts we always had the problem that we never knew what tool was used to kill or to destroy something, is there now a better way? In RR we had for example a KillHook what gave me always the correct information.
- 3. Is there now a way to get the information if the shot was a headshot?

Subject: Re: 4.0 Server Damage

Posted by iRANian on Mon, 07 May 2012 13:57:09 GMT

View Forum Message <> Reply to Message

- 1. The 'StockDamageHook' gets triggered when a non-4.0 player does direct damage and the 'TtDamageHook' gets triggered when a 4.0 player does direct damage, the difference is that the 'TtDamageHook' sends out the ammo used and the bone hit.
- 2. No, but you can write something that gives you 99% accurate information, see the attached file.
- 3. For non-4.0 players you can check the direct damage done with a table of neck shot/head shot damage values for a warhead, the 'TtDamageHook' gives you the bone that a 4.0 player hit. See the attached file for an implementation.

The 1% it fucks up is when a player kills another player with splash or burn damage and he does some really quick weapon switching. The Apache and Orca share the same damage value and warhead and I haven't worked on probably reporting kills done with them yet. The next 4.0 beta will give you the ability to check burn damage (special damage types) so you'll just have to add checking for that and fix the Orca and Apache, and then test it on a server, if you're only using it for a sniper server you shouldn't have any issue and you can remove most of the code. Oh and the squish detection sometimes doesn't trigger.

## File Attachments

1) CustomKillMessages.cpp, downloaded 159 times

Subject: Re: 4.0 Server Damage

Posted by jonwil on Mon, 07 May 2012 14:04:23 GMT

View Forum Message <> Reply to Message

- 1.StockDamageHook is called when damage is done by a < 4.0 player, TtDamageHook is called when damage is done by a 4.0 player.
- 2.On 4.0, you can call Get\_Damage\_Warhead to get the warhead used to carry out damage (i.e. you call it from inside the ::Damaged or ::Killed event of a script, not from inside the damage hook). To convert a string warhead into the number returned by Get\_Damage\_Warhead, call ArmorWarheadManager::Get\_Warhead\_Type.
- 3. No there is no way to tell if it was a head-shot or not.

Subject: Re: 4.0 Server Damage
Posted by EvilWhiteDragon on Tue, 08 May 2012 09:11:26 GMT
View Forum Message <> Reply to Message

JW, you can guestimate whether it was a headshot. Based on the damage tables. Is it possible to do the amount of damage with a weapon of that warhead? No? Then is it possible to do that damage with that warhead divided by 5 to get the normal damage.