
Subject: Brenbot closes after pressing, No error message, wont work.

Posted by [ninjahh](#) on Sun, 03 Oct 2004 00:04:50 GMT

[View Forum Message](#) <> [Reply to Message](#)

I open brenbot..
it closes..
Brenbot wont show error message real quickly..

I got to cmd.exe

i type in the folder..
i type: brenbot to open it..

Then i get the folder line back again...

like brenbot doesn't exist, no error message, just drops back to the folder line..

Ports are set ok..

My brenbot config;

```
#--Start Configuration-IRC-----  
# Edit the information below for your setup.  
# At least edit BotName and IrcChannel.  
BotName = aFEbot01  
BotFullName = BlazeRegulator/BRenBot 1.30 Win32  
IrcServer = irc.n00bstories.com  
IrcPort = 6668  
IrcChannel = #aFEserv01  
#---Q/NickServ-----  
# Enable auth via "Q" or "NickServ" below. Sample input is shown.  
Qauth = 0  
Qusername = RenBot01  
Qpassword = *****  
# Note for NickServ auth you give the name of nickserv and the full ident string as example  
NickServAuth = 1  
NickServName = NickServ  
NickServAuth = identify *****  
#--Windows or Linux-----  
# BotMode MUST be "WIN32" for windows servers, or "LFDS" for Linux servers.  
BotMode = WIN32  
#--Remote Admin Settings-----  
# The next 3 lines should be the same info that is in your server.ini  
# Note: Although it says "Linux" its the same for Win32  
RenRemLinuxHost = 127.0.0.1  
RenRemLinuxPort = 5000  
RenRemLinuxPassword = *****  
#--FDS Installation-----
```

```
# Verify these paths are correct with your Renegade installation.
# Note: FDSLogFilePath must end with the trailing slash (as example below)!!
# Note: Linux users use forward slashes (/) in your paths.
FDSConfigFile = C:\Westwood\RenegadeFDS\Server\Data\svrcfg_cnc.ini
FDSLogFilePath = C:\Westwood\RenegadeFDS\Server\
#--Miscellaneous Settings-----
# Every x minutes the bot will announce a random line from AutoAnnounceFile.
AutoAnnounceInterval = 600
# LadderLookup currently not working. Do not turn it on or it will hang the bot.
EnableLadderLookup = 0
# Set this to 0 or anything but 1 to disable voting.
VotingEnabled = 1
# How long people get to place votes. Default here is 60 seconds.
VotingPeriod = 60
# Set vehicle kick to 1 for Sniper servers
VehicleKick = 0
#--BR Configuration Files-----
# BR Config Files - You shouldn't have to change these names. You can still open them with
notepad.
AutoAnnounceFile = autoannounce.brf
Messagesfile = messages.brf
AdminsFile = admins.brf
MastersFile = masters.brf
KickLogFile = kicklog.brf
BanLogfile = banlog.brf
#--End Configuration-----
```
