Subject: BRenBot Problem (WIN32) Posted by egg098 on Sun, 04 Jan 2004 16:12:56 GMT View Forum Message <> Reply to Message

Quote:#--Start Configuration-IRC-----# Edit the information below for your setup. # At least edit BotName and IrcChannel. BotName = DSBot BotFullName = BlazeRegulator/BRenBot 1.30 Win32 IrcServer = irc.n00bstories.com IrcPort = 6667IrcChannel = #deathserv #---Q/NickServ-----# Enable auth via "Q" or "Nickserv" below. Sample input is shown. Qauth = 0Qusername = RenBot01 Qpassword = mypassword # Note for Nickserv auth you give the name of nickserv and the full ident string as example Nickservauth = 1Nickservname = Nickserv Nickservauth = identify ****** #--Windows or Linux-----# BotMode MUST be "WIN32" for windows servers, or "LFDS" for Linux servers. BotMode = WIN32#--Remote Admin Settings------# The next 3 lines should be the same info that is in your server.ini # Note: Although it says "Linux" its the same for Win32 RenRemLinuxHost = 127.0.0.1 RenRemLinuxPort = 5001RenRemLinuxPassword = ******** #--FDS Installation------# Verify these paths are correct with your Renegade installation. # Note: FDSLogFilePath must end with the trailing slash (as example below)!! # Note: Linux users use forward slashes (/) in your paths. FDSConfigFile = C:\Program Files\Games\Renegade\RenegadeFDS\Server\data\copsandrobbers.ini FDSLogFilePath = C:\Program Files\Games\Renegade\RenegadeFDS\Server\ #--Miscellaneous Settings------# Every x minutes the bot will announce a random line from AutoAnnounceFile. AutoAnnounceInterval = 2# LadderLookup currently not working. Do not turn it on or it will hang the bot. EnableLadderLookup = 0# Set this to 0 or anything but 1 to disable voting. VotingEnabled = 1# How long people get to place votes. Default here is 60 seconds. VotingPeriod = 60# Set vehicle kick to 1 for Sniper servers VehicleKick = 0

#--BR Configuration Files-----# BR Config Files - You shouldn't have to change these names. You can still open them with
notepad.
AutoAnnounceFile = autoannounce.brf
Messagesfile = messages.brf
AdminsFile = admins.brf
MastersFile = masters.brf
KickLogFile = kicklog.brf
BanLogfile = banlog.brf
#--End Configuration------

Is there anything wrong with this? (btw there's no new line after program in the fds config file bit - it's just how it came out on here!)

When I run BRenBot it logs into IRC fine and identifies itself ok. Player updates also appear on the FDS. However no messages from BRenBot appear in IRC and it detects no players, even though there are some in the game. The !msg command 1/2 works - nothing appears from the bot in IRC but it does in the FDS (Egg098@IRC: test)

Page 2 of 2 ---- Generated from Command and Conquer: Renegade Official Forums