
Subject: Suse9.0

Posted by [HLOW]Tomten on Mon, 12 Jan 2004 17:14:25 GMT

[View Forum Message](#) <> [Reply to Message](#)

After my update yesterday I got br to work/startup on suse9.0 from the os I used before suse8.2 but the problem still exist that the bot dont know that players joins the server.

<http://www.renegadeforums.com/viewtopic.php?t=8527>

Exampel if I join my own server the bot prints out "Tomten joined" in mirc but when I do !players or any other player commands or even try to !kick tomten byebye the bot tells me "no such player online".

And yes I start the wrapper first and then brenbot and yes I can telnet in to my server.

I have no ide where the problem is and if this cant get solved I cant have my server up anymore for public use

```
#--Start Configuration-IRC-----
# Edit the information below for your setup.
# At least edit BotName and IrcChannel.
BotName = br-dfcpublic
BotFullName = BlazeRegulator/BRenBot 1.30 Linux
IrcServer = mozilla.se.eu.dal.net
IrcPort = 6667
IrcChannel = #DFC
#---Q/NickServ-----
# Enable auth via "Q" or "NickServ" below. Sample input is shown.
Qauth = 0
Qusername = RenBot01
Qpassword = mypassword
# Note for NickServ auth you give the name of nickserv and the full ident string as example
NickServAuth = 1
NickServName = NickServ
NickServAuth = /nickServ identify *****
#--Windows or Linux-----
# BotMode MUST be "WIN32" for windows servers, or "LFDS" for Linux servers.
BotMode = LFDS
#--Remote Admin Settings-----
# The next 3 lines should be the same info that is in your server.ini
# Note: Although it says "Linux" its the same for Win32
RenRemLinuxHost = 127.0.0.1
RenRemLinuxPort = 4853
RenRemLinuxPassword = *****
#--FDS Installation-----
# Verify these paths are correct with your Renegade installation.
# Note: FDSLogFilePath must end with the trailing slash (as example below)!!
# Note: Linux users use forward slashes (/) in your paths.
```

```
FDSConfigFile = /home/tomten/renegade/public/server/data/svrcfg_cnc.ini
FDSLogFilePath = /home/tomten/renegade/public/server/
#--Miscellaneous Settings-----
# Every x minutes the bot will announce a random line from AutoAnnounceFile.
AutoAnnounceInterval = 300
# LadderLookup currently not working. Do not turn it on or it will hang the bot.
EnableLadderLookup = 0
# Set this to 0 or anything but 1 to disable voting.
VotingEnabled = 0
# How long people get to place votes. Default here is 60 seconds.
VotingPeriod = 60
# Set vehicle kick to 1 for Sniper servers
VehicleKick = 0
#--BR Configuration Files-----
# BR Config Files - You shouldn't have to change these names. You can still open them with
notepad.
AutoAnnounceFile = autoannounce.brf
Messagesfile = messages.brf
AdminsFile = admins.brf
MastersFile = masters.brf
KickLogFile = kicklog.brf
BanLogfile = banlog.brf
#--End Configuration-----
```
