

---

Subject: This make me confused :S

Posted by [TwACharmed](#) on Thu, 01 Apr 2004 08:34:37 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

I have made all the settings and stuff, but still renbot will not open up for me .. maybe i have done something wrong in the settings, im not sure .. but here it is ...

```
#--Start Configuration-IRC-----
# Edit the information below for your setup.
# At least edit BotName and IrcChannel.
BotName = fcusnipebot
BotFullName = BlazeRegulator/BRenBot 1.30 Win32
IrcServer = irc.zirc.org
IrcPort = 6667
IrcChannel = #FCUSNIPESERV
#--Q/NickServ-----
# Enable auth via "Q" or "NickServ" below. Sample input is shown.
Qauth = 0
Qusername = fcusnipebot
Qpassword = *****
# Note for NickServ auth you give the name of nickserv and the full ident string as example
NickServAuth = 1
NickServName = FCUSNIPESERV
NickServAuth = identify fcusnipebot *****
#--Windows or Linux-----
# BotMode MUST be "WIN32" for windows servers, or "LFDS" for Linux servers.
BotMode = WIN32
#--Remote Admin Settings-----
# The next 3 lines should be the same info that is in your server.ini
# Note: Although it says "Linux" its the same for Win32
RenRemLinuxHost = 127.0.0.1
RenRemLinuxPort = 5555
RenRemLinuxPassword = *****
#--FDS Installation-----
# Verify these paths are correct with your Renegade installation.
# Note: FDSLogFilePath must end with the trailing slash (as example below)!!
# Note: Linux users use forward slashes (/) in your paths.
FDSConfigFile = C:\Westwood\RenegadeFDS\Server\Data\svrcfg_cnc.ini
FDSLogFilePath = C:\Westwood\RenegadeFDS2\Server\
#--Miscellaneous Settings-----
# Every x minutes the bot will announce a random line from AutoAnnounceFile.
AutoAnnounceInterval = 600
# LadderLookup currently not working. Do not turn it on or it will hang the bot.
EnableLadderLookup = 0
# Set this to 0 or anything but 1 to disable voting.
VotingEnabled = 1
# How long people get to place votes. Default here is 60 seconds.
```

VotingPeriod = 60

-----  
then in my server ini i have done this settings, and of course the serial, nickname and pw i have in there also ...

LoginServer = [FCU] SNIPESERVER

;  
; This field can be used to specify the Westwood Online matchmaking server  
; to connect to. If left blank, the Renegade Server will connect to the  
; closest matchmaking server. To specify a server to connect to, use one of  
; the names listed above in the section 'Available Westwood Servers'.

LoginServer = [FCU] SNIPESERVER

-----  
RemoteAdminPassword = \*\*\*\*\*

;  
; This is the password required to connect to a server with the RenRem  
; admin too.  
; Slave servers inherit this setting from the master.

RemoteAdminPassword = \*\*\*\*\*

-----  
RemoteAdminPort = 5555

;  
; The port to connect to for remote administration.  
; This can be set per slave. The default slave ports will be shown when  
; connecting to the master with the RenRem tool.

RemoteAdminPort = 5555

-----  
the RemoteAdminPort was set on this one ----> 5555 when i got the server, but what i wonder is, shall i have the irc port or ???

---