

---

Subject: Negotiating Port With Server

Posted by [mr£Ä\\$Ä·z](#) on Wed, 05 Sep 2007 09:45:39 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Hey guys how can i fix that? if i like join some server i cant join it says "Negotiating Port With Server". And some people who like join my Server gets the same... Negotiating Port With Server... how can i fix that?

---

---

Subject: Re: Negotiating Port With Server

Posted by [ExEric3](#) on Wed, 05 Sep 2007 09:57:18 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

1. Servers is running in LAN and external IP is not public.
2. Ports are not forwarded or are blocked.
3. Wrong settings in config files.

Next I think you post this to the wrong section.

---

---

Subject: Re: Negotiating Port With Server

Posted by [mr£Ä\\$Ä·z](#) on Wed, 05 Sep 2007 10:40:35 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

how do i open the ports?

---

---

Subject: Re: Negotiating Port With Server

Posted by [Goztow](#) on Wed, 05 Sep 2007 14:38:03 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

[www.portforward.com](http://www.portforward.com) However, u prolly don't know which ports to open.

Are you running dedicated server or not?

---

---

Subject: Re: Negotiating Port With Server

Posted by [mr£Ä\\$Ä·z](#) on Wed, 05 Sep 2007 15:36:45 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

im running FDS.

---

---

Subject: Re: Negotiating Port With Server

---

Posted by [AoBfrost](#) on Wed, 05 Sep 2007 15:43:07 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

4848 to 4848 with both udp and tcp checked, thats how i fixed mine, since then no one has the error, i used to wonder why people never came in, until my friend tried and i had that problem, so i fixed it, then i noticed 5-6 people would be on ocasionaly.....so you need to forward those ports....

192.168.1.1

Forwarding Area

4848 to 4848 with udp tcp

---

---

Subject: Re: Negotiating Port With Server

Posted by [mr£Ä\\$Ä-z](#) on Wed, 05 Sep 2007 15:56:10 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Should i change the ports in Server.ini or scvgr.ini?

---

---

Subject: Re: Negotiating Port With Server

Posted by [mr£Ä\\$Ä-z](#) on Wed, 05 Sep 2007 16:09:46 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

i tried to check UDP and TCP on firewall but i only can choose 1

---

---

Subject: Re: Negotiating Port With Server

Posted by [AoBfrost](#) on Wed, 05 Sep 2007 16:16:47 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

No, you dont need to change the ports in server.ini, I mean you change the port in 192.168.1.1 in the forwarding area, you dont forward your firewalls ports, you forward your router or switch by typing in 192.168.1.1 then clicking the forwarding range, and then savign it, all routers or switches allow this. If you are hit by a password, then type admin as username and password, if that doesnt work, just try admin as password.

---

---

Subject: Re: Negotiating Port With Server

Posted by [mr£Ä\\$Ä-z](#) on Thu, 06 Sep 2007 00:30:29 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

ähh where can i change the rounterport agin?

---

---

Subject: Re: Negotiating Port With Server  
Posted by [Ethenal](#) on Thu, 06 Sep 2007 01:21:52 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

AoBfrost wrote on Wed, 05 September 2007 11:16No, you dont need to change the ports in server.ini, I mean you change the port in 192.168.1.1 in the forwarding area, you dont forward your firewalls ports, you forward your router or switch by typing in 192.168.1.1 then clicking the forwarding range, and then savign it, all routers or switches allow this. If you are hit by a password, then type admin as username and password, if that doesnt work, just try admin as password.

[Read his post...](#)

---

---

Subject: Re: Negotiating Port With Server  
Posted by [Goztow](#) on Thu, 06 Sep 2007 07:02:11 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

In server.ini check the "port". You can set it to whatever you like, for exemple 5555.

Then go to your router admin (check your router's manual) and search for "virtual server" or "forward ports" or "nat" (sometimes it's called differently). Forward udp port 5555 to the LAN-ip of your server (to check this, do start menu -> run -> cmd -> ipconfig -> enter (it will probably be something like 192.168.1.x)).

If you needm ore help on forwarding ports, check [www.portforward.com](http://www.portforward.com) !

---

---

Subject: Re: Negotiating Port With Server  
Posted by [AoBfrost](#) on Thu, 06 Sep 2007 13:08:54 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

Goztow's post works too, his is more detailed, you can choose any port you want, but alot of people stick with 4848 since it's the default port most forward.

---