Subject: Renegade DOESN'T open when my Server is running... Posted by Goonhaven on Wed, 05 Mar 2008 22:39:24 GMT View Forum Message <> Reply to Message

As the title says, my Command and Conquer Renegade (on C&C first decade) won't do anything when I try to open it whilst running my FDS at the same time. It produces a loading cursor when I click on Renegade and then stops loading about 2 seconds after clicking on it.

Can anyone help me with this i.e. Any suggestions/FACTS?

Here's a print screen of Brenbot and Renegade Master Server up and running at the same time if it helps you:

Subject: Re: Renegade DOESN'T open when my Server is running... Posted by danpaul88 on Wed, 05 Mar 2008 23:11:56 GMT View Forum Message <> Reply to Message

Add +multi to the command line for the FDS server.

Subject: Re: Renegade DOESN'T open when my Server is running... Posted by Goonhaven on Wed, 05 Mar 2008 23:21:18 GMT View Forum Message <> Reply to Message

Sorry to have to act moronic, but what is the command line again - It's when you open up the FDS and are able to type commands in isn't it? With the > sign at the side of each message usually?

Because I typed in +multi and it came up as "+multi" is not a command.

Subject: Re: Renegade DOESN'T open when my Server is running... Posted by danpaul88 on Wed, 05 Mar 2008 23:42:19 GMT View Forum Message <> Reply to Message

Right click the shortcut that opens the FDS, select properties and add +multi to the end of the Target field. Then run the FDS.

Subject: Re: Renegade DOESN'T open when my Server is running... Posted by Goonhaven on Wed, 05 Mar 2008 23:50:40 GMT View Forum Message <> Reply to Message

Ah I see... Thankyou very much for your time, but now when I run the server it doesn't appear in the games list... That's about the 4th problem so far with creating this server and that's following a

Subject: Re: Renegade DOESN'T open when my Server is running... Posted by danpaul88 on Thu, 06 Mar 2008 00:09:21 GMT View Forum Message <> Reply to Message

If you mean the Gamespy games list, you can't see servers hosted on your own IP in the Gamespy games list, it's some sort of wierd bug with GSA.

Subject: Re: Renegade DOESN'T open when my Server is running... Posted by Goonhaven on Thu, 06 Mar 2008 00:10:17 GMT View Forum Message <> Reply to Message

No I mean the WOL Games List.

EDIT: I just noticed that it disconnects me from WOL with the server running, maybe, just maybe, that's why my server doesn't appear in the list..... Although I don't know why it would disconnect me - It could be because I installed a different server.dat file which Crimson suggested on another forum to allow you to join your own game, which I thought might be useful.

Would the WOLProxy 1.1 sticky thread's instructions about changing the host file help at all?

Subject: Re: Renegade DOESN'T open when my Server is running... Posted by Lone0001 on Thu, 06 Mar 2008 01:48:03 GMT View Forum Message <> Reply to Message

Replace your server.dat with this one(and won't need the +multi): http://www.blackintel.org/files/blackintel.server.dat.zip

Note: This makes it so you can start renegade when the server is on and also has some other helpful things.

PS. Sorry to put your help down DanPaul I just think this works much better.

Subject: Re: Renegade DOESN'T open when my Server is running... Posted by danpaul88 on Thu, 06 Mar 2008 11:26:38 GMT View Forum Message <> Reply to Message

Are you logging in to WOL with the same username as the server uses? Because if so that's why you can't see it, as soon as you login with the same username as the server the server gets booted off WOL. You have to give the server a *different* username.

to get on topic

Start renegade after that start the server

kthxbai

Subject: Re: Renegade DOESN'T open when my Server is running... Posted by Goonhaven on Thu, 06 Mar 2008 16:06:53 GMT View Forum Message <> Reply to Message

danpaul88 wrote on Thu, 06 March 2008 05:26Are you logging in to WOL with the same username as the server uses? Because if so that's why you can't see it, as soon as you login with the same username as the server the server gets booted off WOL. You have to give the server a *different* username.

By the 'game username' do you mean the game name?

This is what's in my svrcfg_cnc.ini file as the game name:

; The name of the server as it appears in the lobby list. This has a limit of

; 25 characters in GameSpy mode.

bGameTitle = Goonhaven's AOW Server

The game title contains my username but it isn't just my username, does it have an effect if it has any part of the title with your name in it?

OR is this the game username (in server.ini):

; Nickname =

; This is the Westwood Online nickname you will use when logging into the

; Westwood Online matchmaking system. You can use a nickname from a previous

; Westwood Studios game or apply for a new one by copying the following line

; and pasting it into your web browsers address window

; http://register.westwood.com

Nickname = Goonhaven

Nvm... I found out that it's the one in server.ini and changed it... Now my game works just fine! Apart from the GAME PENDING screen... But I believe I saw a thread on that somewhere. lol, quadruple post...

~Zack

Subject: Re: Renegade DOESN'T open when my Server is running... Posted by Goonhaven on Thu, 06 Mar 2008 17:29:56 GMT View Forum Message <> Reply to Message

You can never have too many posts

Subject: Re: Renegade DOESN'T open when my Server is running... Posted by Genesis2001 on Thu, 06 Mar 2008 18:37:24 GMT View Forum Message <> Reply to Message

Goonhaven wrote on Thu, 06 March 2008 10:29You can never have too many posts

In a row, yes.

EDIT: Has your original question been answered? If so, no need to keep this topic alive.

~Zack

Subject: Re: Renegade DOESN'T open when my Server is running... Posted by Goztow on Thu, 06 Mar 2008 18:46:19 GMT View Forum Message <> Reply to Message

No double, triple or quadruple posts plz. I removed them now and merged the posts in one.

Subject: Re: Renegade DOESN'T open when my Server is running... Posted by cpjok on Fri, 07 Mar 2008 10:41:55 GMT View Forum Message <> Reply to Message

Renegade Wont Come On When A server Is On Have To Put Renegade On Press alt + tab Then Open Server The Click The Minimized Renedae block On Bar At Bottom Then It Will Work Subject: Re: Renegade DOESN'T open when my Server is running... Posted by danpaul88 on Fri, 07 Mar 2008 15:54:35 GMT View Forum Message <> Reply to Message

Or just use the +multi command line or the modified server.dat as mentioned in previous posts, which solved his problem already. Please read a topic before replying to it blindly, especially when your solution is not as good at the ones already posted which actually fix the problem, not just work around it.

Subject: Re: Renegade DOESN'T open when my Server is running... Posted by DarkKnight on Tue, 05 Aug 2008 23:59:16 GMT View Forum Message <> Reply to Message

danpaul88 wrote on Thu, 06 March 2008 05:26Are you logging in to WOL with the same username as the server uses? Because if so that's why you can't see it, as soon as you login with the same username as the server the server gets booted off WOL. You have to give the server a *different* username.

I had the same problem then i thought well i I'll just try and load ren first see what happens. Works fine that way. You don't need to modify any files.

yes i know this is old, someone just showed this to me. sorry didnt look at the date before i replied.

Page 5 of 5 ---- Generated from Command and Conquer: Renegade Official Forums