

---

Subject: Can't Join My Server

Posted by [Sn1per74\\*](#) on Tue, 12 Jun 2012 04:25:51 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Hey Guys,

I'm running a Dedicated Server with TT 4.0 Beta and Brenbot but when I try to join my dedicated server from Renegade it just says "Negotiating Port With Server..." I tried turning off my firewall but it still didn't let me join. Any ideas?

Thanks

---

---

Subject: Re: Can't Join My Server

Posted by [Gen\\_Blacky](#) on Tue, 12 Jun 2012 04:43:56 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

did you open the all the server ports and are you joining through wol.

---

---

Subject: Re: Can't Join My Server

Posted by [Sn1per74\\*](#) on Tue, 12 Jun 2012 04:57:50 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Yes I'm trying to join through WOL and how do I open the server ports?

Thanks for the quick response.

---

---

Subject: Re: Can't Join My Server

Posted by [Gen\\_Blacky](#) on Tue, 12 Jun 2012 05:07:04 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

You usually need to open the upd ports on your router and sometimes on the windows firewall or third party firewall ( windows servers allow all traffic on the firewall by default ). If you don't know how to port forward on your router look at this

<http://www.wikihow.com/Set-up-Port-Forwarding-on-a-Router> or google it.

---

---

Subject: Re: Can't Join My Server

Posted by [Sn1per74\\*](#) on Tue, 12 Jun 2012 06:38:03 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

I followed this

[http://portforward.com/english/routers/port\\_forwarding/Linksys/WRT54G/Command\\_and\\_Conquer\\_Renegade.htm](http://portforward.com/english/routers/port_forwarding/Linksys/WRT54G/Command_and_Conquer_Renegade.htm) and it still won't let me join. Should those instructions work?

---

---

Subject: Re: Can't Join My Server  
Posted by [Gen\\_Blacky](#) on Tue, 12 Jun 2012 10:38:29 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

err idk why you would open all those ports. Just open the ports set in your server.ini default is server port 4848 and gsa query 25300. What ever you have set in your server.ini.

---

Subject: Re: Can't Join My Server  
Posted by [Sn1per74\\*](#) on Tue, 12 Jun 2012 14:26:32 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

That did the trick. You, sir, are a good man.

---