Subject: Linux brenbot problem

Posted by bjorn on Tue, 13 Jan 2004 04:18:56 GMT

View Forum Message <> Reply to Message

i get this error when trying to load brenbot

Starting up renrem thread...

BRenBot 1.31 linux.

brenbot is Copyright 2003-2004 by Daniel Herda & Charles Jones. All Rights reserved.

Fatal Error: Primary IP not found!

Subject: Linux brenbot problem

Posted by snipesimo on Tue, 13 Jan 2004 20:25:27 GMT

View Forum Message <> Reply to Message

Make sure you use "LFDS" and not just LFDS in the config file.

Subject: Linux brenbot problem

Posted by iluvatar on Tue, 13 Jan 2004 20:35:05 GMT

View Forum Message <> Reply to Message

use LFDS in the config file

Subject: Linux brenbot problem

Posted by [HLOW]Tomten on Tue, 13 Jan 2004 23:32:40 GMT

View Forum Message <> Reply to Message

Yepp LFDS should it be.

in 1.30 you used "LFDS" but in 1.31 you only use LFDS

Subject: Linux brenbot problem

Posted by bjorn on Wed, 14 Jan 2004 06:43:33 GMT

View Forum Message <> Reply to Message

When i just use LFDS i get:

Starting up renrem thread...

BRenBot 1.31 linux.

brenbot is Copyright 2003-2004 by Daniel Herda & Charles Jones. All Rights reserved.

Fatal Error: Primary IP not found!

When i use "LFDS" i get:

BotMode must be either LFDS or WIN32!

My config looks like this: #--Start Configuration-IRC-----# Edit the information below for your setup. # At least edit BotName and IrcChannel. BotName = Renegade BotFullName = BlazeRegulator/BRenBot 1.30 IrcServer = irc.undernet.org IrcPort = 6667IrcChannel = #Globe #---Q/NickServ------# Enable auth via "Q" or "Nickserv" below. Sample input is shown. Qauth = 0Qusername = RenBot01 Qpassword = mypassword # Note for Nickserv auth you give the name of nickserv and the full ident string as example Nickservauth = 0Nickservname = Nickserv Nickservauth = identify RenBot01 mypassword #--Windows or Linux------# BotMode MUST be "WIN32" for windows servers, or "LFDS" for Linux servers. BotMode = LFDS#--Remote Admin Settings------# The next 3 lines should be the same info that is in your server.ini # Note: Although it says "Linux" its the same for Win32 RenRemLinuxHost = 127.0.0.1 RenRemLinuxPort = 4853 RenRemLinuxPassword = ****** # Verify these paths are correct with your Renegade installation. # Note: FDSLogFilePath must end with the trailing slash (as example below)!! # Note: Linux users use forward slashes (/) in your paths. FDSConfigFile = /home/games/Server/data/svrfg_cnc.ini FDSLogFilePath = /home/games/Server/ #--Miscellaneous Settings-----# Every x minutes the bot will announce a random line from AutoAnnounceFile. AutoAnnounceInterval = 600 # LadderLookup currently not working. Do not turn it on or it will hang the bot. EnableLadderLookup = 0# Set this to 0 or anything but 1 to disable voting. VotingEnabled = 1 # How long people get to place votes. Default here is 60 seconds. VotingPeriod = 60 # Set vehicle kick to 1 for Sniper servers VehicleKick = 0

#--BR Configuration Files-----

BR Config Files - You shouldn't have to change these names. You can still open them with notepad.

AutoAnnounceFile = autoannounce.brf

Messagesfile = messages.brf

AdminsFile = admins.brf

MastersFile = masters.brf

KickLogFile = kicklog.brf

BanLogfile = banlog.brf

#--End Configuration------

BR Config Files - You shouldn't have to change these names. You can still open them with notepad.

AutoAnnounceFile = autoannounce.brf

Messagesfile = messages.brf

AdminsFile = admins.brf

MastersFile = masters.brf

KickLogFile = kicklog.brf

BanLogfile = banlog.brf

#--End Configuration------

Subject: Linux brenbot problem

Posted by [HLOW]Tomten on Wed, 14 Jan 2004 11:29:35 GMT

View Forum Message <> Reply to Message

What linux OS are you using on your server?

Subject: Linux brenbot problem

Posted by biorn on Fri. 23 Jan 2004 10:07:38 GMT

View Forum Message <> Reply to Message

redhat8

Subject: Linux brenbot problem

Posted by mac on Fri, 23 Jan 2004 14:00:23 GMT

View Forum Message <> Reply to Message

Check if /sbin/ifconfig is executable by your brenbot user. brenbot calls this to find out the primary ip.