
Subject: This make me confused :S

Posted by [TwACharmed](#) on Thu, 01 Apr 2004 08:34:37 GMT

[View Forum Message](#) <> [Reply to Message](#)

I have made all the settings and stuff, but still renbot will not open up for me .. maybe i have done something wrong in the settings, im not sure .. but here it is ...

```
#--Start Configuration-IRC-----
# Edit the information below for your setup.
# At least edit BotName and IrcChannel.
BotName = fcusnipebot
BotFullName = BlazeRegulator/BRenBot 1.30 Win32
IrcServer = irc.zirc.org
IrcPort = 6667
IrcChannel = #FCUSNIPESERV
#--Q/NickServ-----
# Enable auth via "Q" or "NickServ" below. Sample input is shown.
Qauth = 0
Qusername = fcusnipebot
Qpassword = *****
# Note for NickServ auth you give the name of nickserv and the full ident string as example
NickServAuth = 1
NickServName = FCUSNIPESERV
NickServAuth = identify fcusnipebot *****
#--Windows or Linux-----
# BotMode MUST be "WIN32" for windows servers, or "LFDS" for Linux servers.
BotMode = WIN32
#--Remote Admin Settings-----
# The next 3 lines should be the same info that is in your server.ini
# Note: Although it says "Linux" its the same for Win32
RenRemLinuxHost = 127.0.0.1
RenRemLinuxPort = 5555
RenRemLinuxPassword = *****
#--FDS Installation-----
# Verify these paths are correct with your Renegade installation.
# Note: FDSLogFilePath must end with the trailing slash (as example below)!!
# Note: Linux users use forward slashes (/) in your paths.
FDSConfigFile = C:\Westwood\RenegadeFDS\Server\Data\svrcfg_cnc.ini
FDSLogFilePath = C:\Westwood\RenegadeFDS2\Server\
#--Miscellaneous Settings-----
# Every x minutes the bot will announce a random line from AutoAnnounceFile.
AutoAnnounceInterval = 600
# LadderLookup currently not working. Do not turn it on or it will hang the bot.
EnableLadderLookup = 0
# Set this to 0 or anything but 1 to disable voting.
VotingEnabled = 1
# How long people get to place votes. Default here is 60 seconds.
```

VotingPeriod = 60

then in my server ini i have done this settings, and of course the serial, nickname and pw i have in there also ...

LoginServer = [FCU] SNIPESERVER

;
; This field can be used to specify the Westwood Online matchmaking server
; to connect to. If left blank, the Renegade Server will connect to the
; closest matchmaking server. To specify a server to connect to, use one of
; the names listed above in the section 'Available Westwood Servers'.

LoginServer = [FCU] SNIPESERVER

RemoteAdminPassword = *****

;
; This is the password required to connect to a server with the RenRem
; admin tool.
; Slave servers inherit this setting from the master.

RemoteAdminPassword = *****

RemoteAdminPort = 5555

;
; The port to connect to for remote administration.
; This can be set per slave. The default slave ports will be shown when
; connecting to the master with the RenRem tool.

RemoteAdminPort = 5555

the RemoteAdminPort was set on this one ----> 5555 when i got the server, but what i wonder is, shall i have the irc port or ???

Subject: This make me confused :S

Posted by [TwACharmed](#) on Thu, 01 Apr 2004 08:40:49 GMT

[View Forum Message](#) <> [Reply to Message](#)

I also wonder if i have to restart the server before everything take effect ?

Subject: This make me confused :S
Posted by [TnTaTTack](#) on Thu, 01 Apr 2004 09:25:16 GMT
[View Forum Message](#) <> [Reply to Message](#)

```
nickservauth=1  
nickservname=nickserv  
nickservauth=identify *****
```

```
in server.ini  
logonserver=european server(or pacific or usa server)  
allowremoteadmin=true  
port&pass leave it  
grtz  
aTTack
```

Subject: This make me confused :S
Posted by [Crimson](#) on Thu, 01 Apr 2004 10:41:13 GMT
[View Forum Message](#) <> [Reply to Message](#)

Well, your first problem is you should have your server on irc.n00bstories.com

Just kiddin'

Subject: This make me confused :S
Posted by [Uberfahr](#) on Thu, 01 Apr 2004 11:08:27 GMT
[View Forum Message](#) <> [Reply to Message](#)

Somewhere in the dark space of my brain, I remember that Qpassword must be exactly 8 characters. It seems there are only 5 *. But maybe I m wrong. Please try.

Subject: This make me confused :S
Posted by [TwACharmed](#) on Thu, 01 Apr 2004 13:14:57 GMT
[View Forum Message](#) <> [Reply to Message](#)

i have tryed it all but still the same .. it open up but close down fast again and i have no chance to see what it say

Subject: This make me confused :S
Posted by [Uberfahr](#) on Thu, 01 Apr 2004 13:31:49 GMT
[View Forum Message](#) <> [Reply to Message](#)

hmm, I cant see anything unusual, but maybe this:

FDSConfigFile = C:\Westwood\RenegadeFDS\Server\Data\svrcfg_cnc.ini
FDSLogFilePath = C:\Westwood\RenegadeFDS2\Server\

do you have 2 fds? RenegadeFDS and RenegadeFDS2?

Subject: This make me confused :S
Posted by [TwACharmed](#) on Thu, 01 Apr 2004 16:45:54 GMT
[View Forum Message](#) <> [Reply to Message](#)

well i have 2 servers one 12 players sniper and then one 32 player normal .. u think it can be that who is the problem ?

Subject: This make me confused :S
Posted by [Uberfahr](#) on Thu, 01 Apr 2004 19:35:51 GMT
[View Forum Message](#) <> [Reply to Message](#)

I dont think so, but who knows. Please remove the "2" just to try and try the servers separately.

Subject: This make me confused :S
Posted by [Blazer](#) on Thu, 01 Apr 2004 21:49:46 GMT
[View Forum Message](#) <> [Reply to Message](#)

It looks like you are using the config for one server, and the logfile for the second server....

Subject: This make me confused :S
Posted by [Majin Vegeta](#) on Thu, 01 Apr 2004 22:22:45 GMT
[View Forum Message](#) <> [Reply to Message](#)

Charmed i can help you set it up all you have to do is ask when im around :S

Subject: This make me confused :S
Posted by [c4girl14](#) on Tue, 20 Apr 2004 06:49:44 GMT
[View Forum Message](#) <> [Reply to Message](#)

NM.....

Subject: This make me confused :S

Posted by [RadioactiveKangaroo](#) on Mon, 24 May 2004 21:47:24 GMT

[View Forum Message](#) <> [Reply to Message](#)

Just keep doubleclicking on it, it works for me.... just a bug in XP i guess...

Subject: This make me confused :S

Posted by [EkkoTheGekko](#) on Wed, 26 May 2004 11:57:19 GMT

[View Forum Message](#) <> [Reply to Message](#)

just like RadioactiveKangaroo said, keep doubleclicking, I had the same problem too. You can also go there in your dos prompt en then keep pushing up -> enter etc...
After a while it should start.

good luck;)

EkkoTheGekko
